

# VOLVO VIDA Installation Guide

Phone:86-15072360818



X-Horse Electronics Co., Ltd.

Any questions, please don't hesitate to contact us. Email: sales01@cardiag.co.uk Skype:cardiag.co.uk sales02@cardiag.co.uk Yahoo:cardiag.service@yahoo.com



### **Table of Contents**

1.	Install VOLVO VIDA	3
2.	Install MVCI Driver	9
	Start VOLVO VIDA	12





## 1. Install VOLVO VIDA



To install VOLVO VIDA, Driver C: must be NTFS format, with at least 10G free space. IE 6.0 needed.

 Put the VIDA installation DVD into DVDROM, setup will run automatically.



If the installation program does not run automatically, please manually run:

Install\DVD\Vida\_dvdheader\Main\setup.exe




#### Select VIDA All-in-one






Select language, then Click Next






#### Click Next






#### Select Yes



The whole process of installation will last 30-70 minutes, according to the performance of PC.



#### Click Finish




**Reboot PC is NEEDED.** 




## 2. Install MVCI Driver

#### Click Next






Select installation folder, then click Next




Click Install to begin installation




Any questions, please don't hesitate to contact us. Email: sales01@cardiag.co.uk 15kype:cardiag.co.uk sales02@cardiag.co.uk Yahoo:cardiag.service@yahoo.com



• Installing...



Click Finish to exit installation



Any questions, please don't hesitate to contact us. Email: sales01@cardiag.co.uk Skype:cardiag.co.uk sales02@cardiag.co.uk Yahoo:cardiag.service@yahoo.com



## 3. Start VOLVO VIDA

Double-Click VIDA All-in-one icon on Desktop



Input the Username: admin, then click LOGIN



VIDA
VEHICLE INFORMATION & DIAGNOSTICS FOR AFTERSALES

Username: admin
» LOG IN
REGISTRATION GUIDE FOR SUBSCRIPTION
Problems with log in?
Please contact your local helpdesk
This machine is registered as msuser2, VIDA Version: VIDA2010A

Any questions, please don't hesitate to contact us. Email: sales01@cardiag.co.uk \Skype:cardiag.co.uk sales02@cardiag.co.uk \Yahoo:cardiag.service@yahoo.com



Click START, then click PERFORM COMPUTER SETTINGS



 Click COMMUNICATION TOOL, click Dice, select J2534 MVCI - VOLVO, then Click OK





Any questions, please don't hesitate to contact us. Email: sales01@cardiag.co.uk 1Skype:cardiag.co.uk sales02@cardiag.co.uk Yahoo:cardiag.service@yahoo.com



Click VEHICLE PROFILE, then Click READ VEHICLE.
 Select vehicle options, and then click OK.
 Click DIAGNOSTICS to start diagnostic.

